# Chapter 3 Transport Layer

#### A note on the use of these ppt slides:


We're making these slides freely available to all (faculty, students, readers). They're in PowerPoint form so you can add, modify, and delete slides (including this one) and slide content to suit your needs. They obviously represent a *lot* of work on our part. In return for use, we only ask the following:

☐ If you use these slides (e.g., in a class) in substantially unaltered form, that you mention their source (after all, we'd like people to use our book!)☐ If you post any slides in substantially unaltered form on a www site, that you note that they are adapted from (or perhaps identical to) our slides, and note our copyright of this material.

Thanks and enjoy! JFK/KWR

All material copyright 1996-2007

J.F Kurose and K.W. Ross, All Rights Reserved



Computer Networking: A Top Down Approach 4<sup>th</sup> edition. Jim Kurose, Keith Ross Addison-Wesley, July 2007.

# Chapter 3: Transport Layer

#### Our goals:

- understand principles behind transport layer services:
  - multiplexing/ demultiplexing
  - o reliable data transfer
  - flow control
  - congestion control

- learn about transport layer protocols in the Internet:
  - UDP: connectionless transport
  - TCP: connection-oriented transport
  - TCP congestion control


# Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer

- □ 3.5 Connection-oriented transport: TCP
  - segment structure
  - o reliable data transfer
  - flow control
  - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

## Transport services and protocols

- provide logical communication between app processes running on different hosts
- transport protocols run in end systems
  - send side: breaks app messages into segments, passes to network layer
  - rcv side: reassembles segments into messages, passes to app layer
- more than one transport protocol available to apps
  - Internet: TCP and UDP



## Transport vs. network layer


- network layer: logical communication between hosts
- transport layer: logical communication between processes
  - relies on, enhances, network layer services

#### Household analogy:

- 12 kids sending letters to 12 kids
- processes = kids
- app messages = lettersin envelopes
- □ hosts = houses
- transport protocol = Ann and Bill
- network-layer protocolpostal service

# Internet transport-layer protocols

- reliable, in-order delivery (TCP)
  - congestion control
  - flow control
  - connection setup
- unreliable, unordered delivery: UDP
  - no-frills extension of "best-effort" IP
- services not available:
  - delay guarantees
  - bandwidth guarantees



# Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer

- 3.5 Connection-oriented transport: TCP
  - o segment structure
  - o reliable data transfer
  - flow control
  - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

# Multiplexing/demultiplexing


#### Demultiplexing at rcv host:

delivering received segments to correct socket

= socket = process


#### Multiplexing at send host:

gathering data from multiple sockets, enveloping data with header (later used for demultiplexing)



## How demultiplexing works

- host receives IP datagrams
  - each datagram has source IP address, destination IP address
  - each datagram carries 1 transport-layer segment
  - each segment has source, destination port number
- host uses IP addresses & port numbers to direct segment to appropriate socket



TCP/UDP segment format

# Connectionless demultiplexing

Create sockets with port numbers:

```
DatagramSocket mySocket1 = new
  DatagramSocket(12534);
```

DatagramSocket mySocket2 = new
 DatagramSocket(12535);


UDP socket identified by two-tuple:

(dest IP address, dest port number)

- When host receives UDP segment:
  - checks destination port number in segment
  - directs UDP segment to socket with that port number
- ☐ IP datagrams with different source IP addresses and/or source port numbers directed to same socket

## Connectionless demux (cont)

DatagramSocket serverSocket = new DatagramSocket(6428);




SP provides "return address"

## Connection-oriented demux


- □ TCP socket identified by 4-tuple:
  - source IP address
  - source port number
  - o dest IP address
  - dest port number
- recv host uses all four values to direct segment to appropriate socket

- Server host may support many simultaneous TCP sockets:
  - each socket identified by its own 4-tuple
- Web servers have different sockets for each connecting client
  - non-persistent HTTP will have different socket for each request

# Connection-oriented demux (cont)



# Connection-oriented demux: Threaded Web Server



# Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer

- □ 3.5 Connection-oriented transport: TCP
  - segment structure
  - o reliable data transfer
  - flow control
  - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

## UDP: User Datagram Protocol [RFC 768]

- "no frills," "bare bones" Internet transport protocol
- "best effort" service, UDP segments may be:
  - o lost
  - delivered out of order to app
- connectionless:
  - o no handshaking between UDP sender, receiver
  - each UDP segment handled independently of others

#### Why is there a UDP?

- no connection establishment (which can add delay)
- simple: no connection state at sender, receiver
- small segment header
- no congestion control: UDP can blast away as fast as desired

### UDP: more

often used for streaming multimedia apps

Length, in

segment,

including

header

bytes of UDP

loss tolerant

o rate sensitive

other UDP uses

- O DNS
- SNMP
- reliable transfer over UDP:
   add reliability at
   application layer
  - application-specific error recovery!

source port # dest port #

length checksum

Application
data
(message)

UDP segment format

## UDP checksum

<u>Goal</u>: detect "errors" (e.g., flipped bits) in transmitted segment

#### Sender:

- treat segment contents as sequence of 16-bit integers
- checksum: addition (1's complement sum) of segment contents
- sender puts checksum value into UDP checksum field


#### Receiver:

- compute checksum of received segment
- check if computed checksum equals checksum field value:
  - NO error detected
  - YES no error detected.
     But maybe errors
     nonetheless? More later

....

# Internet Checksum Example

- Note
  - When adding numbers, a carryout from the most significant bit needs to be added to the result
- □ Example: add two 16-bit integers




# Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer

- 3.5 Connection-oriented transport: TCP
  - segment structure
  - o reliable data transfer
  - flow control
  - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

## Principles of Reliable data transfer


- important in app., transport, link layers
- top-10 list of important networking topics!



- (a) provided service
- characteristics of unreliable channel will determine complexity of reliable data transfer protocol (rdt)

### Principles of Reliable data transfer


- important in app., transport, link layers
- top-10 list of important networking topics!



 characteristics of unreliable channel will determine complexity of reliable data transfer protocol (rdt)


## Principles of Reliable data transfer

- important in app., transport, link layers
- top-10 list of important networking topics!



 characteristics of unreliable channel will determine complexity of reliable data transfer protocol (rdt)

### Reliable data transfer: getting started



### Reliable data transfer: getting started

#### We' ||:


- incrementally develop sender, receiver sides of reliable data transfer protocol (rdt)
- consider only unidirectional data transfer
  - but control info will flow on both directions!
- use finite state machines (FSM) to specify sender, receiver

state: when in this "state" next state uniquely determined by next event



#### Rdt1.0: reliable transfer over a reliable channel

- underlying channel perfectly reliable
  - o no bit errors
  - no loss of packets
- separate FSMs for sender, receiver:
  - o sender sends data into underlying channel
  - o receiver read data from underlying channel



sender

receiver

#### Rdt2.0: channel with bit errors

- underlying channel may flip bits in packet
  - o checksum to detect bit errors
- the question: how to recover from errors:
  - acknowledgements (ACKs): receiver explicitly tells sender that pkt received OK
  - negative acknowledgements (NAKs): receiver explicitly tells sender that pkt had errors
  - o sender retransmits pkt on receipt of NAK
- new mechanisms in rdt2.0 (beyond rdt1.0):
  - o error detection
  - o receiver feedback: control msgs (ACK, NAK) rcvr->sender

## rdt2.0: FSM specification

rdt\_send(data)
snkpkt = make\_pkt(data, checksum)
udt\_send(sndpkt)

Wait for
call from
above

rdt\_rcv(rcvpkt) &&
isNAK(rcvpkt)

udt\_send(sndpkt)

rdt\_rcv(rcvpkt) && isACK(rcvpkt)

A

sender

#### receiver

rdt\_rcv(rcvpkt) &&
corrupt(rcvpkt)


udt\_send(NAK)

Wait for
call from
below


rdt\_rcv(rcvpkt) &&
notcorrupt(rcvpkt)

extract(rcvpkt,data)
deliver\_data(data)
udt\_send(ACK)

## rdt2.0: operation with no errors



### rdt2.0: error scenario



## rdt2.0 has a fatal flaw!

# What happens if ACK/NAK corrupted?

- sender doesn't know what happened at receiver!
- can't just retransmit: possible duplicate


#### Handling duplicates:

- sender retransmits current pkt if ACK/NAK garbled
- sender adds sequence number to each pkt
- receiver discards (doesn't deliver up) duplicate pkt


#### stop and wait

Sender sends one packet, then waits for receiver response

### rdt2.1: sender, handles garbled ACK/NAKs



### rdt2.1: receiver, handles garbled ACK/NAKs



## rdt2.1: discussion

#### Sender:

- seq # added to pkt
- two seq. #'s (0,1) will suffice. Why?
- must check if received ACK/NAK corrupted
- twice as many states
  - state must "remember" whether "current" pkt has 0 or 1 seq. #


#### Receiver:

- must check if received packet is duplicate
  - state indicates whether0 or 1 is expected pktseq #
- note: receiver can not know if its last ACK/ NAK received OK at sender

## rdt2.2: a NAK-free protocol

- □ same functionality as rdt2.1, using ACKs only
- instead of NAK, receiver sends ACK for last pkt received OK
  - o receiver must explicitly include seq # of pkt being ACKed
- duplicate ACK at sender results in same action as NAK: retransmit current pkt

### rdt2.2: sender, receiver fragments




#### rdt3.0: channels with errors and loss


#### New assumption:

- underlying channel can also lose packets (data or ACKs)
  - checksum, seq. #, ACKs, retransmissions will be of help, but not enough
- <u>Approach:</u> sender waits "reasonable" amount of time for ACK
- retransmits if no ACK received in this time
- if pkt (or ACK) just delayed (not lost):
  - retransmission will be duplicate, but use of seq.
     #'s already handles this
  - receiver must specify seq# of pkt being ACKed
- requires countdown timer


#### rdt3.0 sender




#### rdt3.0 in action



(a) operation with no loss



#### rdt3.0 in action



#### Performance of rdt3.0

- rdt3.0 works, but performance stinks
- □ ex: 1 Gbps link, 15 ms prop. delay, 8000 bit packet:


$$d_{trans} = \frac{L}{R} = \frac{8000 \text{bits}}{10^9 \text{bps}} = 8 \text{ microseconds}$$

O U sender: utilization - fraction of time sender busy sending

$$U_{\text{sender}} = \frac{L/R}{RTT + L/R} = \frac{.008}{30.008} = 0.00027$$

- 1KB pkt every 30 msec -> 33kB/sec thruput over 1 Gbps link
- network protocol limits use of physical resources!

# rdt3.0: stop-and-wait operation




$$U_{\text{sender}} = \frac{L/R}{RTT + L/R} = \frac{.008}{30.008} = 0.00027$$

# Pipelined protocols

Pipelining: sender allows multiple, "in-flight", yetto-be-acknowledged pkts

- o range of sequence numbers must be increased
- buffering at sender and/or receiver




(a) a stop-and-wait protocol in operation

(b) a pipelined protocol in operation

Two generic forms of pipelined protocols: go-Back-N, selective repeat

# Pipelining: increased utilization



# Pipelining Protocols

#### Go-back-N: big picture:

- Sender can have up to N unacked packets in pipeline
- Rcvr only sends cumulative acks
  - Doesn't ack packet if there's a gap
- Sender has timer for oldest unacked packet
  - If timer expires, retransmit all unacked packets

#### Selective Repeat: big pic

- Sender can have up to N unacked packets in pipeline
- Rcvr acks individual packets
- Sender maintains timer for each unacked packet
  - When timer expires, retransmit only unack packet


# Selective repeat: big picture

- Sender can have up to N unacked packets in pipeline
- Rcvr acks individual packets
- Sender maintains timer for each unacked packet
  - When timer expires, retransmit only unack packet

# Go-Back-N

#### Sender:

- k-bit seq # in pkt header
- "window" of up to N, consecutive unack' ed pkts allowed




- ACK(n): ACKs all pkts up to, including seq # n "cumulative ACK"
  - o may receive duplicate ACKs (see receiver)
- timer for each in-flight pkt
- timeout(n): retransmit pkt n and all higher seq # pkts in window

#### GBN: sender extended FSM

```
rdt send(data)
                       if (nextseqnum < base+N) {
                          sndpkt[nextseqnum] = make pkt(nextseqnum,data,chksum)
                          udt send(sndpkt[nextsegnum])
                          if (base == nextseqnum)
                           start timer
                          nextsegnum++
                       else
                        refuse data(data)
   base=1
   nextsegnum=1
                                          timeout
                                          start timer
                             Wait
                                          udt send(sndpkt[base])
                                          udt send(sndpkt[base+1])
rdt rcv(rcvpkt)
 && corrupt(rcvpkt)
                                          udt send(sndpkt[nextsegnum-1]
                         rdt rcv(rcvpkt) &&'
                           notcorrupt(rcvpkt)
                         base = getacknum(rcvpkt)+1
                         If (base == nextseqnum)
                           stop timer
                          else
                           start timer
```


#### GBN: receiver extended FSM



# ACK-only: always send ACK for correctly-received pkt with highest in-order seq #

- may generate duplicate ACKs
- o need only remember expectedseqnum
- out-of-order pkt:
  - discard (don't buffer) -> no receiver buffering!
  - Re-ACK pkt with highest in-order seq #


# GBN in action



# Selective Repeat

- receiver *individually* acknowledges all correctly received pkts
  - buffers pkts, as needed, for eventual in-order delivery to upper layer
- sender only resends pkts for which ACK not received
  - sender timer for each unACKed pkt
- sender window
  - N consecutive seq #'s
  - again limits seq #s of sent, unACKed pkts

#### Selective repeat: sender, receiver windows



(b) receiver view of sequence numbers

# Selective repeat

#### -sender

#### data from above:

if next available seq # in window, send pkt

#### timeout(n):

resend pkt n, restart timer

ACK(n) in [sendbase,sendbase+N]:

- mark pkt n as received
- ☐ if n smallest unACKed pkt, advance window base to next unACKed seq #

# receiver pkt n in [rcvbase, rcvbase+N-1] send ACK(n) out-of-order: buffer in-order: deliver (also deliver buffered, in-order pkts), advance window to

pkt n in [rcvbase-N,rcvbase-1]


next not-yet-received pkt

 $\Box$  ACK(n)

otherwise:

ignore


#### Selective repeat in action



# Selective repeat: dilemma

#### Example:

- seq #'s: 0, 1, 2, 3
- window size=3
- receiver sees no difference in two scenarios!
- incorrectly passes duplicate data as new in (a)
- Q: what relationship between seq # size and window size?



# Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer

- □ 3.5 Connection-oriented transport: TCP
  - segment structure
  - o reliable data transfer
  - flow control
  - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

### TCP: Overview

RFCs: 793, 1122, 1323, 2018, 2581

- point-to-point:
  - one sender, one receiver
- reliable, in-order byte
  steam:
  - o no "message boundaries"
- pipelined:
  - TCP congestion and flow control set window size
- send & receive buffers

- full duplex data:
  - bi-directional data flow in same connection
  - MSS: maximum segment size
- connection-oriented:
  - handshaking (exchange of control msgs) init's sender, receiver state before data exchange
- □ flow controlled:
  - sender will not overwhelm receiver



# TCP segment structure

URG: urgent data (generally not used)

ACK: ACK # valid

PSH: push data now (generally not used)

RST, SYN, FIN: connection estab (setup, teardown commands)

> Internet checksum' (as in UDP)

dest port # source port # sequence number acknowledgement number head not len used UAPRSF Receive window checksum Urg data pnter Options (variable length) application data (variable length)

32 bits

counting by bytes of data (not segments!)

> # bytes rcvr willing to accept


# TCP seq. #'s and ACKs

#### Seq. #'s:

 byte stream "number" of first byte in segment's data

#### ACKs:

- seq # of next byte expected from other side
- cumulative ACK
- Q: how receiver handles out-of-order segments
  - A: TCP spec doesn't say, - up to implementor



# TCP Round Trip Time and Timeout

- Q: how to set TCP timeout value?
- Ionger than RTT
  - but RTT varies
- too short: premature timeout
  - unnecessary retransmissions
- too long: slow reaction to segment loss

- Q: how to estimate RTT?
- SampleRTT: measured time from segment transmission until ACK receipt
  - o ignore retransmissions
- SampleRTT will vary, want estimated RTT "smoother"
  - average several recent measurements, not just current SampleRTT


# TCP Round Trip Time and Timeout

EstimatedRTT =  $(1-\alpha)$ \*EstimatedRTT +  $\alpha$ \*SampleRTT

- Exponential weighted moving average
- influence of past sample decreases exponentially fast
- $\Box$  typical value:  $\alpha = 0.125$

#### Example RTT estimation:

RTT: gaia.cs.umass.edu to fantasia.eurecom.fr



### TCP Round Trip Time and Timeout

#### Setting the timeout

- EstimtedRTT plus "safety margin"
  - large variation in EstimatedRTT -> larger safety margin
- first estimate of how much SampleRTT deviates from EstimatedRTT:

```
DevRTT = (1-\beta)*DevRTT + \beta*|SampleRTT-EstimatedRTT| (typically, \beta = 0.25)
```

#### Then set timeout interval:

```
TimeoutInterval = EstimatedRTT + 4*DevRTT
```

# Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer

- 3.5 Connection-oriented transport: TCP
  - segment structure
  - o reliable data transfer
  - flow control
  - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

# TCP reliable data transfer

- TCP creates rdt service on top of IP's unreliable service
- Pipelined segments
- Cumulative acks
- TCP uses single retransmission timer

- Retransmissions are triggered by:
  - o timeout events
  - duplicate acks
- Initially consider simplified TCP sender:
  - ignore duplicate acks
  - ignore flow control, congestion control

# TCP sender events:

#### data rcvd from app:

- Create segment with seq #
- seq # is byte-stream number of first data byte in segment
- start timer if not already running (think of timer as for oldest unacked segment)
- □ expiration interval:
  TimeOutInterval

#### timeout:

- retransmit segment that caused timeout
- restart timer

#### Ack rcvd:

- If acknowledges previously unacked segments
  - update what is known to be acked
  - start timer if there are outstanding segments

```
NextSeqNum = InitialSeqNum
SendBase = InitialSeqNum
loop (forever) {
  switch(event)
  event: data received from application above
     create TCP segment with sequence number NextSeqNum
     if (timer currently not running)
         start timer
     pass segment to IP
      NextSegNum = NextSegNum + length(data)
  event: timer timeout
     retransmit not-yet-acknowledged segment with
          smallest sequence number
     start timer
  event: ACK received, with ACK field value of y
     if (y > SendBase) {
         SendBase = y
         if (there are currently not-yet-acknowledged segments)
              start timer
 } /* end of loop forever */
```


# TCP sender (simplified)

#### Comment:


 SendBase-1: last cumulatively ack'ed byte Example:

SendBase-1 = 71;
y= 73, so the rcvr
wants 73+;
y > SendBase, so
that new data is
acked

#### TCP: retransmission scenarios



# TCP retransmission scenarios (more)



Cumulative ACK scenario

# TCP ACK generation [RFC 1122, RFC 2581]

Event at Receiver	TCP Receiver action
Arrival of in-order segment with expected seq #. All data up to expected seq # already ACKed	Delayed ACK. Wait up to 500ms for next segment. If no next segment, send ACK
Arrival of in-order segment with expected seq #. One other segment has ACK pending	Immediately send single cumulative ACK, ACKing both in-order segments
Arrival of out-of-order segment higher-than-expect seq. # . Gap detected	Immediately send duplicate ACK, indicating seq. # of next expected byte
Arrival of segment that partially or completely fills gap	Immediate send ACK, provided that segment starts at lower end of gap

# Fast Retransmit

- Time-out period often relatively long:
  - long delay before resending lost packet
- □ Detect lost segments via duplicate ACKs.
  - Sender often sends many segments back-toback
  - If segment is lost, there will likely be many duplicate ACKs.

- □ If sender receives 3 ACKs for the same data, it supposes that segment after ACKed data was lost:
  - fast retransmit: resend segment before timer expires




Figure 3.37 Resending a segment after triple duplicate ACK Layer 3-72

## Fast retransmit algorithm:

```
event: ACK received, with ACK field value of y
              if (y > SendBase) {
                 SendBase = y
                 if (there are currently not-yet-acknowledged segments)
                     start timer
              else {
                   increment count of dup ACKs received for y
                   if (count of dup ACKs received for y = 3) {
                      resend segment with sequence number y
a duplicate ACK for
                                 fast retransmit
already ACKed segment
```


# Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer

- 3.5 Connection-oriented transport: TCP
  - segment structure
  - o reliable data transfer
  - flow control
  - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

## TCP Flow Control

receive side of TCP connection has a receive buffer:




 app process may be slow at reading from buffer

#### flow control

sender won't overflow receiver's buffer by transmitting too much, too fast

speed-matching service: matching the send rate to the receiving app's drain rate

## TCP Flow control: how it works



(Suppose TCP receiver discards out-of-order segments)

- spare room in buffer
- = RcvWindow
- = RcvBuffer-[LastByteRcvd -LastByteRead]

- Rcvr advertises spare room by including value of RcvWindow in segments
- Sender limits unACKed data to RcvWindow
  - quarantees receive buffer doesn't overflow

# Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer

- 3.5 Connection-oriented transport: TCP
  - segment structure
  - o reliable data transfer
  - flow control
  - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

## TCP Connection Management

- Recall: TCP sender, receiver establish "connection" before exchanging data segments
- initialize TCP variables:
  - o seq. #s
  - buffers, flow control info (e.g. RcvWindow)
- client: connection initiator

```
Socket clientSocket = new
Socket("hostname", "port
number");
```

Server: contacted by client
Socket connectionSocket =
welcomeSocket.accept();

#### Three way handshake:

- Step 1: client host sends TCP SYN segment to server
  - specifies initial seq #
  - o no data
- Step 2: server host receives SYN, replies with SYNACK segment
  - server allocates buffers
  - specifies server initial seq.
- Step 3: client receives SYNACK, replies with ACK segment, which may contain data


#### TCP Connection Management (cont.)

#### Closing a connection:

client closes socket:
 clientSocket.close();

Step 1: client end system sends TCP FIN control segment to server

Step 2: server receives FIN, replies with ACK. Closes connection, sends FIN.




### TCP Connection Management (cont.)

Step 3: client receives FIN, replies with ACK.


 Enters "timed wait" will respond with ACK to received FINs

Step 4: server, receives ACK. Connection closed.

Note: with small modification, can handle simultaneous FINs.



## TCP Connection Management (cont)



# Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer


- 3.5 Connection-oriented transport: TCP
  - segment structure
  - o reliable data transfer
  - flow control
  - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control


## Principles of Congestion Control


#### Congestion:

- □ informally: "too many sources sending too much data too fast for *network* to handle"
- different from flow control!
- manifestations:
  - lost packets (buffer overflow at routers)
  - long delays (queueing in router buffers)
- □ a top-10 problem!

- two senders, two receivers
- one router, infinite buffers
- no retransmission









- large delays when congested
- maximum achievable throughput

- one router, *finite* buffers
- sender retransmission of lost packet




- $\square$  always:  $\lambda_{in} = \lambda_{out}$  (goodput)
- "perfect" retransmission only when loss:  $\lambda' > \lambda_{in}$  out,
- retransmission of delayed (not lost) packet makes  $\lambda_{in}$ (than perfect case) for same  $\lambda_{out}$




- "costs" of congestion:
- more work (retrans) for given "goodput"
- unneeded retransmissions: link carries multiple copies of pkt

- four senders
- multihop paths
- timeout/retransmit

 $\underline{\textbf{Q:}}$  what happens as  $\lambda_{\text{in}}$  and  $\lambda_{\text{in}}'$  increase ?





#### Another "cost" of congestion:

□ when packet dropped, any "upstream transmission capacity used for that packet was wasted!

### Approaches towards congestion control

#### Two broad approaches towards congestion control:

# End-end congestion control:

- no explicit feedback from network
- congestion inferred from end-system observed loss, delay
- approach taken by TCP

# Network-assisted congestion control:

- routers provide feedback to end systems
  - single bit indicating congestion (SNA, DECbit, TCP/IP ECN, ATM)
  - explicit rate sender should send at

### Case study: ATM ABR congestion control


#### ABR: available bit rate:

- "elastic service"
- if sender's path
   "underloaded":
  - sender should use available bandwidth
- if sender's path congested:
  - sender throttled to minimum guaranteed rate

# RM (resource management) cells:

- sent by sender, interspersed with data cells
- bits in RM cell set by switches ("network-assisted")
  - NI bit: no increase in rate (mild congestion)
  - CI bit: congestion indication
- RM cells returned to sender by receiver, with bits intact

#### Case study: ATM ABR congestion control



- two-byte ER (explicit rate) field in RM cell
  - o congested switch may lower ER value in cell
  - o sender' send rate thus maximum supportable rate on path
- □ EFCI bit in data cells: set to 1 in congested switch
  - o if data cell preceding RM cell has EFCI set, sender sets CI bit in returned RM cell

# Chapter 3 outline


- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer

- □ 3.5 Connection-oriented transport: TCP
  - segment structure
  - o reliable data transfer
  - flow control
  - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

# TCP congestion control: additive increase, multiplicative decrease

- Approach: increase transmission rate (window size), probing for usable bandwidth, until loss occurs
  - additive increase: increase CongWin by 1 MSS every RTT until loss detected
  - multiplicative decrease: cut CongWin in half after loss

Saw tooth behavior: probing for bandwidth



## TCP Congestion Control: details

- Roughly,

rate = 
$$\frac{CongWin}{RTT}$$
 Bytes/sec

Congwin is dynamic, function of perceived network congestion

# How does sender perceive congestion?

- loss event = timeout *or*3 duplicate acks
- □ TCP sender reduces rate (CongWin) after loss event

#### three mechanisms:

- O AIMD
- slow start
- conservative after timeout events


## TCP Slow Start

- When connection begins,CongWin = 1 MSS
  - Example: MSS = 500bytes & RTT = 200 msec
  - o initial rate = 20 kbps
- available bandwidth may be >> MSS/RTT
  - desirable to quickly ramp up to respectable rate

 When connection begins, increase rate exponentially fast until first loss event

## TCP Slow Start (more)

- When connection begins, increase rate exponentially until first loss event:
  - double CongWin every RTT
  - done by incrementing CongWin for every ACK received
- □ Summary: initial rate is slow but ramps up exponentially fast



# Refinement: inferring loss


- □ After 3 dup ACKs:
  - O Congwin is cut in half
  - window then grows linearly
- But after timeout event:
  - CongWin instead set to 1 MSS;
  - window then grows exponentially
  - to a threshold, then grows linearly

#### Philosophy:

- □ 3 dup ACKs indicates network capable of delivering some segments
- □ timeout indicates a "more alarming" congestion scenario

## Refinement

- Q: When should the exponential increase switch to linear?
- A: When CongWin gets to 1/2 of its value before timeout.



#### Implementation:

- Variable Threshold
- At loss event, Threshold is set to 1/2 of CongWin just before loss event

#### Summary: TCP Congestion Control

- □ When CongWin is below Threshold, sender in slow-start phase, window grows exponentially.
- □ When CongWin is above Threshold, sender is in congestion-avoidance phase, window grows linearly.
- □ When a triple duplicate ACK occurs, Threshold set to CongWin/2 and CongWin set to Threshold.
- □ When timeout occurs, Threshold set to CongWin/2 and CongWin is set to 1 MSS.

## TCP sender congestion control

State	Event	TCP Sender Action	Commentary
Slow Start (SS)	ACK receipt for previously unacked data	CongWin = CongWin + MSS, If (CongWin > Threshold) set state to "Congestion Avoidance"	Resulting in a doubling of CongWin every RTT
Congestion Avoidance (CA)	ACK receipt for previously unacked data	CongWin = CongWin+MSS * (MSS/CongWin)	Additive increase, resulting in increase of CongWin by 1 MSS every RTT
SS or CA	Loss event detected by triple duplicate ACK	Threshold = CongWin/2, CongWin = Threshold, Set state to "Congestion Avoidance"	Fast recovery, implementing multiplicative decrease. CongWin will not drop below 1 MSS.
SS or CA	Timeout	Threshold = CongWin/2, CongWin = 1 MSS, Set state to "Slow Start"	Enter slow start
SS or CA	Duplicate ACK	Increment duplicate ACK count for segment being acked	CongWin and Threshold not changed

# TCP throughput

- What's the average throughout of TCP as a function of window size and RTT?
  - Ignore slow start
- Let W be the window size when loss occurs.
- When window is W, throughput is W/RTT
- □ Just after loss, window drops to W/2, throughput to W/2RTT.
- □ Average throughout: .75 W/RTT

## TCP Futures: TCP over "long, fat pipes"


- Example: 1500 byte segments, 100ms RTT, want 10
   Gbps throughput
- □ Requires window size W = 83,333 in-flight segments
- Throughput in terms of loss rate:

$$\frac{1.22 MSS}{RTT\sqrt{L}}$$

- $\Box$   $\rightarrow$  L = 2·10<sup>-10</sup> Wow
- □ New versions of TCP for high-speed

## TCP Fairness


Fairness goal: if K TCP sessions share same bottleneck link of bandwidth R, each should have average rate of R/K



# Why is TCP fair?

#### Two competing sessions:

- Additive increase gives slope of 1, as throughout increases
- multiplicative decrease decreases throughput proportionally



## Fairness (more)

#### Fairness and UDP

- Multimedia apps often do not use TCP
  - do not want rate throttled by congestion control
- Instead use UDP:
  - pump audio/video at constant rate, tolerate packet loss
- Research area: TCP friendly

# Fairness and parallel TCP connections

- nothing prevents app from opening parallel connections between 2 hosts.
- Web browsers do this
- Example: link of rate R supporting 9 connections;
  - new app asks for 1 TCP, gets rate R/10
  - new app asks for 11 TCPs, gets R/2!

## Chapter 3: Summary

- principles behind transport layer services:
  - multiplexing, demultiplexing
  - o reliable data transfer
  - o flow control
  - congestion control
- instantiation and implementation in the Internet
  - O UDP
  - O TCP

#### <u>Next:</u>

- leaving the network "edge" (application, transport layers)
- □ into the network "core"